
ARM 2022 Changes


Study Rules

New Interface





1 of 3

New Interface



New Interface






Conditional Rules

Define when a study rule should be activated, based on another field's contents

E.g. Require Crop Planting Rate, only when Planting Date is filled in




Boost your company's "global rule set", to address specific rules for certain trial types

1 of 2

Conditional Rules

Condition can be based on multiple fields, or multiple values within single field



2 of 2

Site Description

Application Not Applied

Identify an application that is not applied


- Purpose: Retain a planned application code, but denote that it was not performed
- Process: Toggle NA button above application

Application Description									
	□ X NA		₽ × NA	1	₽ × N	Α			
	Α		В		C (not applied)				
Application Date	Apr-15-2022	~	Jun-3-2022	~		~			
Appl. Start Time	2:30 PM		10:00 AM						
Application Method	SPRAY	~	SPRAY	~	SPRAY	~			
Application Timing	ATPLAN	~	POSPOS	~	POSPOS	~			
Application Placement	BROSOI	~	BROFOL	~	BROFOL	~			

Application Not Applied

Impact:

- Enter a deviation to explain circumstances
- Not included in product calc's
- 'NA' applications display with strikethrough
- Appl. Date field can be blank without failing validation if marked 'NA'



New Fields

Many new fields added to editors in Protocols and Trials

- New Regulations tab with Harvest Destruction section
- More columns in Trial Location table
- Crop Description expanded in protocol
 - ...and now separate from Pest Description too



See ARM 2022.5 Field Changes PDF for more details:


https://gdmdata.com/media/documents/Change logs/ARM 2022.5 Field Changes.pdf

ARM Powered by GDM Solutions

Repeating Sections

Empty record automatically added at end of repeating sections

- Easier to add additional items without "Insert Repeating Section" command
- Excludes Application, Crop, and Pest sections




Crop/Pest in use

Verification for whether a **crop/pest is used** in the trial

"In use" if:

- Information entered in Crop/Pest
 Stage at Appl sections, or
- Referenced in an assessment column that has data

Warning when <u>deleting</u> crop/pest in use




Validation warning for when <u>not</u> in use



Insert SE from File

New shortcut button on SE Definitions: load an SE from your PC


- Saves time after creating an SE from an existing assessment
- After loading from file once, the SE is added to the SE Name Favorites list



Set as Default

"Set as Default" can be used in rich text fields

Can include default instructions / required language for reports




ARM Powered by GDM Solutions

Validation Lists

Validation Lists

Personal List is now Favorites


- Favorites tab on list window (no more Display Personal/Master)
- Master List is simply "Display All"
- Shortcut buttons add or remove from Favorites




Validation Lists

"User-built" lists are improved

 Shortcut "X" button to remove from the list



Open list in "edit" mode to adjust existing items




Assessment Data

Assessment Image

New dialog for previewing and zooming assessment images

- Improves performance for high-resolution photos
- Workflow improved for using image to review or take ratings




Data Review

Column Diagnostics

Now highlights values that indicate a failure of data to meet AOV assumptions

P-values < 0.05 imply failure of data to meet tested assumption




ARM Powered by GDM Solutions

Column Diagnostics

Recognizes "selected treatments" Action Codes (EC, ETn)

Recommended actions now calculated <u>after</u> excluding the data




Normality Tests

Include all info used on Column Diagnostics in AOV report

Added Shapiro-Wilk test to report

- Choose how statistical tests are reported
 - Test statistic, **p-value**, or both

	Treatment	Rate	3*			
No.	Name	Rate Unit				
1	Untreated Check		4.55 a			
2	Tub	0.5 l/ha	1.93 b			
3	Tub	1 l/ha	1.53 b			
4	Tilt 250	0.5 l/ha	1.83 b			
5	Mico 60	1.5 l/ha	2.70 b			
1) P=.05			1.264		
	ndard Deviation			0.821		
CV				32.76		
Lev	ene's Prob(F)			0.73		
	hapiro-Wilk) [^]		0	.5027		
P(Skewness) [^]			0.2652			
P(K	urtosis)^		0	.8741		





Trial Signature

Trial Signature

Updates to the new Trial Signature feature:

- Trial can be signed at any trial status (previously only for 'Final')
- Signing a trial with status = Final (or later) starts an Audit Trail
 - All further changes are logged and prompted to provide a reason







Trial Signature

New study rule to require a signature at particular Trial Status

- Field determines what status triggers rule
- Condition determines who needs to sign





 ARM prompts for signature when trial status is set (if validation passes)




Validation

Trial Status

Validation is performed automatically when Trial Status is changed

Purpose: Study rules may become active with a different Status

Impact: Resolve validation issues before adding your signature to trial (or printing, sending, etc.)




Print Reports

Summary Reports

Summary reports now always start on a new page in report

- Summary reports = AOV Means, Assessment Data Summary, etc.
- Select 'Remove page break...' to combine report sections on same page when there is room
- Summary reports take up most of a page, so do not fit well if combined with other reports




Profile

Send License Details

New 'Send License Details' button

- Find it on the Profile and Request Customization dialogs
- Share ARM license details in an email




Multi-factor Designs

Multi-factor studies

Level Description added to Settings dialog

- Same information on the Trial Map dialog
- Now available in a protocol, too!



Treatments

Validation updates

Added support for **Biological Entity Dispensers** as treatments

- Treatment Type: BIOENT
- Formulation Units: BIOEN/D (biological entities per dispenser)
- Formulation Type: BD (biological entity dispenser)
- Rate Units: dispensers per area or per number of plants
 - D/A, D/ha, D/1000 FT2, D/100 m2, D/1000 plants, D/10000 m2 LWA


Trt No.	Type	Treatment Name	Form Conc	Form Unit	Form Type		Rate Unit	Other Rate	Other Rate Unit
1	BIOENT	Biological Entity Dispenser	1000	BIOEN/D	BD	15	D/1000 FT2	16.1	D/100 m2

Data Analysis


R software update

ARM now supports R versions 4.2.0 and newer

- No additional installation/update needed at this time
- R is used behind-the-scenes for analysis, reporting
- R users export Column Diagnostics script to R:



Previously would give an error if R version was too new.



ARM Mobile

Export images

Export images from ARM Mobile with or without data

- Purpose: Allows user to export images, comments, or GPS during or after assessment export.
- Example: One researcher can enter only data, another can take plot pictures. Both can export the same assessment data column – images will import "on top of" data.

