

Printing to a label sheet

The standard way to print labels within ARM is to a label sheet, which contains a grid of labels on a single page. ARM contains pre-defined defaults for specific Avery label sheets (e.g. Avery 3451 or Avery L6103), or you can customize the options to fit the specific label sheet to use. Specify the number of columns and rows per sheet, as well as the label height and width and the margins before the left label column and above the top label.

Tip: Use the Preview tab in ARM, and then print to regular printer paper before printing with a particular

label sheet. Then compare with the sheet to ensure that the labels will print as expected, before wasting expensive label sheets. Once the configuration is correct, then save a report set for the label, and insert the label sheet for printing.

Trial: G-AII7_Fung

Name: Tub Trt: 3 Plot: 101

Trial: G-All7_Fung

Trt: 2 Plot: 104

Trial: G-All7_Fung Name: Tilt 250

Trt: 4 Plot: 204

Trial: G-All7_Fung

Name: Tub Trt: 2 Plot: 201

Trial: G-AII7 Fund

Name: Tub

Printing to a continuous/roll printer

Some label printers use a roll of labels, printing on one at a time instead of a whole grid. This can be useful when only needing a few labels, instead of printing on only a portion of a 30-label sheet.



This is a fundamentally different approach than the standard reports or labels, so there are several changes that need to be made in ARM to use a such a printer.

Label Sheet Report Options	
Report Options Report Preview	
Label sheet description	
Columns per sheet:	1 🜲
Rows per sheet:	1
Label height:	5.87cm
Label width:	10.16cm
Margins	
Before left label column:	0.0cm
Above top label:	0.0cm

- 1. Set the Label Sheet Report Options as follows:
 - a. Set 'Columns per sheet' and 'Rows per sheet' to 1.
 - b. Set Label height and width to match the dimensions of label in use.
 - c. Set Margins options to 0.
- 2. Set the printer Paper Size to the size of the label in use.
 - a. From the Print dialog, select Print Setup, then select the Properties button.
 - b. Find the Paper Size option and set it to the dimensions of the label. (The Properties dialog will differ depending on the printer.)

Tip: On the Print dialog, use Preview to view the first label to be printed. Then select to print just 1 page, to ensure that the labels will print as expected. Once the configuration is correct, then save a report set for the label, and include all pages to print all of the labels.

Name: Untreated Check Trt: 1 Plot: 102 Name: Tilt 250 Trt: 4 Plot: 103 Trial: G-All7_Fung Name: Mico 60+Fungol rt: 5 Plot: 105

Trial: G-All7_Fung Name: Mico 60+Fungol

Trial: G-All7 Euno

Trt: 5 Plot: 203

Trial: G-All7 Fung Name: Tub Trt: 3 Plot: 301 Trial: G-All7 Fund Trial: G-All7_Fung Name: Untreated Check Trt: 1 Plot: 205

Trial: G-All7_Fung Name: Tub Trt: 3 Plot: 202

Trial: G-All7 Fung

Trial: G-All7_Fung rt: 2 Plot: 302

Trial: G-All7 Fund